

UTGO Image Reduction & Photometry Guide

Introduction:

The UTGO pipeline can be found pre-installed on Keck Machine in the ‘UTGO_Pipeline’ folder or on Github here:

https://github.com/tiplunkett/UTGO_Pipeline

There is further documentation in this folder about how each script works, which I recommend reading. This document is the hands-on guide and will gloss over some details already listed.

Before beginning, go into the terminal and activate the reduction environment ('red' on Keck Machine) and change into the UTGO_Pipeline directory!

Part 1 – Image Reduction/Calibration:

The first phase of any good analysis is correcting your images for sources of noise. This typically involves 3 main steps: bias-subtraction, dark current subtraction and flat-fielding. I will not go into full details of what these are, instead you can read Howell (2006) for background. Here I present your 2 choices for reduction using my pipeline, both using Prose (Garcia et al. 2021).

Automatic Reduction:

There is an automated script that reduces all new data taken from the Harlingtonen 50cm each day via a Cron job. This achieved through the scripts ‘update_calibs.py’, ‘autoReduce.py’ and ‘ReductionBot.py’, which live in the ‘UTGO_Pipeline’ folder.

To use:

- Copy the night’s folder (i.e 20231008) containing your data from the Planewave computer to the **‘/home/obs/Work/Data/[Year]’** folder via WinSCP.
- Each day at 7 am, the reduction begins on any new data.
- These reduced images will be outputted to object folders, with sub folders for filter in **‘/home/obs/Work/Reduced/[object]’**.

Disclaimer: more thorough reduction may be necessary (especially if there is unusual noise/systematics in your data or the calibration frames aren’t great).




Figure 1. Example of the structure of the ‘Reduced’ folder.

Manual Reduction:

If you want more control over the calibration frames used to reduce your data, you can use the script ‘reduce_H50.py’. First, copy your raw science frames to a new folder. Then copy in the desired calibration frames into this folder. Finally, type:

python reduce_h50.py [path2fits] [depth]

This will perform the reduction and save the new files into new sub-folders (labelled by image dimension) in the original directory.

```
[(red) a4-cf-99-84-4d-5c-dyn:TomUtils-main tp22$ python reduce_H50.py /Users/tp22/Desktop/TPHE 0
RUN Parsing FITS: 100%|██████████| 103/103 [00:00<00:00, 178.30images/s]
RUN Parsing FITS: 100%|██████████| 103/103 [00:00<00:00, 2109.79images/s]
      date      telescope filter   type    target  width height  files
id
9  2023-04-12  PlaneWave 50cm     i  bias  HIP 39961  2048  2048    10
5  2023-04-20  PlaneWave 50cm     i  dark      A  2048  2048    10
6  2023-09-13  PlaneWave 50cm     B  flat  HIP 99570  2048  2048     4
8  2023-09-13  PlaneWave 50cm     V  flat  HIP 99570  2048  2048     6
7  2023-09-13  PlaneWave 50cm     g  flat  HIP 99570  2048  2048     6
10 2023-09-13  PlaneWave 50cm     r  flat  HIP 99570  2048  2048     7
4  2023-10-01  PlaneWave 50cm     B  light  TPHE-A  2048  2048    15
2  2023-10-01  PlaneWave 50cm     V  light  TPHE-A  2048  2048    15
3  2023-10-01  PlaneWave 50cm     g  light  TPHE-A  2048  2048    15
1  2023-10-01  PlaneWave 50cm     r  light  TPHE-A  2048  2048    15
RUN Parsing FITS: 100%|██████████| 43/43 [00:00<00:00, 136.51images/s]
INFO buidling bad pixels map
RUN 100%|██████████| 15/15 [00:06<00:00,  2.19images/s]
INFO buidling bad pixels map
RUN 100%|██████████| 15/15 [00:02<00:00,  7.49images/s]
INFO buidling bad pixels map
RUN 100%|██████████| 15/15 [00:02<00:00,  6.84images/s]
```

Figure 2. Example command line output using reduce_H50.py




Figure 3. Example of the input and output folder structures for `reduce_H50.py`

Part 2 – Photometry:

Now that you have reduced your data, you are ready to perform photometry to get your light curves. But first, you must ask yourself: what type of photometry do I need? There are 3 types available to you currently: simple aperture, differential aperture and difference imaging. To start, change into the ‘**UTGO_Pipeline/Photometry**’ directory.

Simple Aperture Photometry (SAP):

SAP is the most basic photometry method and most prone to error. It involves defining a circular region (the ‘aperture’) around a target and then summing up the count values, scaling to electrons and subtracting the local background noise to find the flux/magnitude.

To perform SAP, you can use either the ‘aper_phot.py’ or ‘forced_phot.py’ script. The ‘aper_phot.py’ can be used when your target has good SNR across all frames, which might not be the case for some transients. To use:

```
cd UTGO_Pipeline/Photometry
```

```
python aper_phot.py [path2images] [ID] [autoAperture] [verbose]
```

This will output a calibrated light curve to the ‘Phot_Outputs’ subfolder, using SExtractor or PhotUtils to extract a catalogue and find zeropoints for the image (using the same aperture). Note, the auto-aperture will be the one that maximises the SNR in the first frame.

The ‘forced_phot.py’ script can be used to perform forced photometry anywhere on your image. Note, it does not centroid your aperture, so be very careful with placement. To use, type:

python forced_phot.py [path2folder] [depth] [astr] [vis]

If you select ‘y’ for [vis], this will display a sample image for you to visually choose the centroid of your target. This is done by double clicking on the image. If you select ‘n’, then be prepared to type the (x,y) coordinates of your target into the terminal.

The outputted file will be in .csv format, containing the JD, aperture flux, instrumental magnitude, errors and an calibrated magnitude.

Summary:

1. Run the aperture (aper_phot.py) or forced photometry script (forced_phot.py) on reduced images folder.
2. Select target position either by clicking on image or manually entering coordinates.
3. Profit???

Differential Aperture Photometry (DAP):

This type of photometry is best used in cases where you have an isolated target and absolute calibration is not needed (i.e you just need to know how the light curve changed relative to some starting value). Hence, this is commonly used for transit photometry when searching for exoplanets.

To perform DAP, type:

```
python diff_phot.py [path2calibratedfiles] [auto] [threshold]  
[obs_date]
```

The [auto] argument informs the code on how you want to perform the photometry. In the case of ‘y’, this will present two options. The first will use the algorithm defined in Broeg et al. 2005 to find the ‘optimal’ comparison stars for the target. Otherwise, GAIA DR2 is queried to find the 5 closest stars by colour and magnitude for comparison stars (in the case where differential refraction causes systematics). If you choose ‘n’, this will give you manual choice of your comp. stars by entering their IDs (shown in a pop-up reference frame window) in a comma separated list.

This code will output files to a new subfolder called ‘phot_outputs’, containing a .csv file with your light curve (and other systematics), along with a basic summary plot of the observations, image showing the chosen comparison stars and a plot of the PSF model.

Summary:

1. Run differential photometry script (diff_phot.py)
2. Select your target via number listed beneath star. Zoom in if field is crowded.
3. Profit?





Figure 6. Output images from the DAP script (diffphot_pipe.py).

Difference Imaging Analysis (DIA) Photometry:

The final form of photometry is best used in situations where your target is located in a very crowded field (such as the Galactic Bulge) or close to another object. To do this, we have two choices. If you want an industry-standard, tried and tested code that is optimised for microlensing, then you should use the pySIS code. However, the process of using this code with our data is lengthy and takes some experimentation. A guide is included for this in a separate file.

If you want an easy/quick (but possibly less thorough/clean) option, you can use the ‘dia_phot.py’ script instead. This has the benefit of being fully integrated into the existing pipeline and consistent with other photometry scripts. To perform DIA photometry, type:

```
python dia_phot.py [Path] [Visual] [AutoRef] [Stack] [Redo]  
[Verbose]
```

Here, the path flag is to directory with all the reduced files. If you would like the code to find the best frames (i.e lowest seeing and background) and stack them, you would use [AutoRef] = y and [Stack] = y. Otherwise, you can choose an individual file that you prefer for the reference by using [AutoRef] = n. The [Redo] flag tells the code if you want to redo subtraction (so should be set to ‘y’ if doing from scratch), otherwise only the photometry steps will be performed. The subtraction is performed in parallel, but can take a reasonable amount of time if the seeing is bad (i.e a larger kernel size is used).

The code will output the reference and registered frames in a new ‘DIA’ sub-directory, along with the photometry catalogue on the reference frame (in ‘ref_phot.csv’), a light curve for the target calibrated to GAIA DR2 (in ‘target_dia_phot.csv’) and a diagnostic plot showing examples of differencing for each night (in ‘diff_check.png’).




Figure 7. The visual selection option for dia_phot.py




Figure 8. The output of dia_phot.py, including the ‘diff_check.png’ diagnostic plot showing the differencing for each unique night of observation.

Part 3 – Stacking:

If you have a very faint target with poor SNR, you may need to co-add multiple frames to get good measurements. To do this, type:

```
cd UTGO_Pipeline/Utils
```

```
python stacker.py [path2folder] [depth] [method] [period]
```

The method will either be ‘swarp’ or default to median stack. The period tells it how many images to stack per co-add, i.e if you pass 5 it will stack every 5 images or if you type ‘D’ it will stack all the frames from a night.